


Deprovision someone

Wiki Home	Download Grouper	Grouper Guides	Community Contributions	Developer Resources	Deployment Guide
---------------------------	----------------------------------	--------------------------------	-----------------------------------------	-------------------------------------	----------------------------------

To deprovision a user, click Miscellaneous



Click Deprovisioning

+ Create new group

Quick links

My groups

My folders

My favorites

My services

My activity

Miscellaneous

Admin UI

Lite UI

Browse folders

Root

apps

wiki

Home > Miscellaneous

Miscellaneous

Functions across the repository

Inherited privileges

Subject API diagnostics

Instrumentation

Loader jobs

Attestation

Deprovisioning

Select an affiliation

Home > Miscellaneous > Deprovisioning

View deprovisioned users

More actions

Recently deprovisioned entities

Deprovision User

Users who have been deprovisioned recently

Affiliation

employee

Select an affiliation to deprovision. These are configured by the admin.

There are no recently deprovisioned users

More actions Deprovision user

Deprovision a user

More actions ▼

Deprovision a user who has left the institution

Affiliation

employee ▼

Select an affiliation to deprovision. These are configured by the admin.

Member name or ID:

te

- description.test.subject.0
- description.test.subject.1
- description.test.subject.2
- description.test.subject.3
- description.test.subject.4
- description.test.subject.5
- description.test.subject.6
- description.test.subject.7
- description.test.subject.8
- description.test.subject.9

Search for a user, View user access to deprovision

Home > Miscellaneous > Deprovisioning

Deprovision a user

More actions ▾

Deprovision a user who has left the institution

Affiliation

employee ▾

Select an affiliation to deprovision. These are configured by the admin.

Member name or ID:

description.test.subject.0

Enter an entity name or ID, or [search for an entity](#).

View user access to deprovision

Below are the directly assigned memberships and privileges. Objects which are restricted from deprovisioning are not shown by default.

Deprovision user and remove access

<input checked="" type="checkbox"/>	Folder	Object	Object type	Group Member?	Privileges
<input checked="" type="checkbox"/>	apps	wiki	Folder	NA	Create
<input checked="" type="checkbox"/>	apps : wiki	wikiAdmins	Group	true	
<input checked="" type="checkbox"/>	apps : wiki	wikiAttr	Attribute	NA	Read
<input checked="" type="checkbox"/>	apps : wiki	wikiUsers	Group	true	Read, Update

Select what needs to be deprovisioned, and Deprovision user and remove access

Note, if something shouldn't be configured, you should probably [edit the settings on a folder / group / attribute](#)

Success: the user was deprovisioned

+ Create new group ▾

Quick links

My groups

My folders

My favorites

My services

My activity

Miscellaneous

Admin UI

Lite UI

Browse folders

Home > Miscellaneous > Deprovisioning

View deprovisioned users

More actions ▾

Users who have been deprovisioned recently

Affiliation

employee ▾

Select an affiliation to deprovision. These are configured by the admin.

Deprovisioned users

my name is test.subject.0

Under the Miscellaneous menu option you can View deprovisioned users.

To view users who were NOT deprovisioned use the [Deprovisioning Report](#).