


# Deprovisioning settings on folders / groups / attributes

<a href="#">Wiki Home</a>	<a href="#">Download Grouper</a>	<a href="#">Grouper Guides</a>	<a href="#">Community Contributions</a>	<a href="#">Developer Resources</a>	<a href="#">Grouper Website</a>
---------------------------	----------------------------------	--------------------------------	---	-------------------------------------	---------------------------------

To access the Deprovisioning settings, click on a folder or group or attribute (generally will be a folder, maybe the root folder)



Click on Deprovisioning actions

# apps

Edit folder

More actions ▾

More ▾

Folder contents

Privileges

More ▾

## Deprovisioning report on group

Deprovisioning actions ▾

This report shows assignments to entities who have been deprovisioned. This means they no longer have the affiliation at your institution. Generally you should remove all access that deprovisioned entities have. Do this by checking the checkboxes and clicking "Remove access". If access should not be removed, then instead, click "Certify that these entries should remain". You will not receive an email about these privileges again until other entities are deprovisioned.

View deprovisioning settings

**Edit deprovisioning settings**

Deprovisioning main

Deprovisioning report

Clear last certify date

Run deprovisioning daemon

**Note: there are no deprovisioned entities with privileges on this folder**

**View or edit settings**

### Edit folder deprovisioning settings

Deprovisioning actions ▾

**Affiliation**

employee ▾

Affiliation is a set of users to be deprovisioned. Affiliations are configured by the administrator.

**Deprovisioning**

Yes, has direct deprovisioning configuration ▾

If this affiliation has deprovisioning configuration directly assigned to this object

**Deprovision**

Yes, deprovision entities that leave ▾

When someone is deprovisioned from this affiliation, should they be removed from this object? Default: true

**Folder scope**

All objects in this folder or subfolders ▾

Do these deprovisioning settings affect objects in this folder and all subfolders (default) or only objects directly in this folder

**Send email**

No, do not send email alerts ▾

If an email should be sent when someone is deprovisioned or needs to be deprovisioned

**Show for removal**

Yes, show this object on deprovisioning screen ▾

On the deprovisioning screen should this object be displayed

**Autoselect for removal**

Yes ▾

On the deprovisioning screen should the checkbox be checked by default

**Allow deprovisioned assignments**

No ▾

If an entity is deprovisioned, allow assignments between that entity and this object. Default is no, veto assignments.

**Auto change loader**

Yes ▾

If this relates to a loader job, then should deprovisioned entities not be allowed to be loaded. Default is true

Save

Cancel