


Deprovisioning settings on folders / groups / attributes

Wiki Home	Download Grouper	Grouper Guides	Community Contributions	Developer Resources	Deployment Guide
---------------------------	----------------------------------	--------------------------------	---	-------------------------------------	----------------------------------

To access the Deprovisioning settings, click on a folder or group or attribute (generally will be a folder, maybe the root folder)



Click on Deprovisioning actions

apps

Edit folder

More actions ▾

More ▾

Folder contents

Privileges

More ▾

Deprovisioning report on group

This report shows assignments to entities who have been deprovisioned. This means they no longer have the affiliation at your institution. Generally you should remove all access that deprovisioned entities have. Do this by checking the checkboxes and clicking "Remove access". If access should not be removed, then instead, click "Certify that these entries should remain". You will not receive an email about these privileges again until other entities are deprovisioned.

Note: there are no deprovisioned entities with privileges on this folder

Deprovisioning actions ▾

View deprovisioning settings

Edit deprovisioning settings

Deprovisioning main

Deprovisioning report

Clear last certify date

Run deprovisioning daemon

View or edit settings

Edit folder deprovisioning settings

Deprovisioning actions ▾

Affiliation

employee ▾

Affiliation is a set of users to be deprovisioned. Affiliations are configured by the administrator.

Deprovisioning

Yes, has direct deprovisioning configuration ▾

If this affiliation has deprovisioning configuration directly assigned to this object

Deprovision

Yes, deprovision entities that leave ▾

When someone is deprovisioned from this affiliation, should they be removed from this object? Default: true

Folder scope

All objects in this folder or subfolders ▾

Do these deprovisioning settings affect objects in this folder and all subfolders (default) or only objects directly in this folder

Send email

No, do not send email alerts ▾

If an email should be sent when someone is deprovisioned or needs to be deprovisioned

Show for removal

Yes, show this object on deprovisioning screen ▾

On the deprovisioning screen should this object be displayed

Autoselect for removal

Yes ▾

On the deprovisioning screen should the checkbox be checked by default

Allow deprovisioned assignments

No ▾

If an entity is deprovisioned, allow assignments between that entity and this object. Default is no, veto assignments.

Auto change loader

Yes ▾

If this relates to a loader job, then should deprovisioned entities not be allowed to be loaded. Default is true

Save

Cancel